

config_inicial.txt

NOTA LUIZ FRANCISCO BOZO: CONFIGURAÇÕES INICIAIS DO TSUNAMI

<BOTÃO STATUS>

Status

System Status Wireless Router v2.0.1(72) SN-05AT10590479 v3.0.4

IP Address 10.0.0.1
Contact Contact Name
Name Wireless Router (mudei p/ RSU_empresa com sucesso)
Location Contact Location
Object ID 1.3.6.1.4.1.11898.2.4.9
Up Time (DD:HH:MM:SS) 00:00:31:33

system

Information

System Name

Note: Configure Satellite to use this Base Station System Name if you want Satellite to register only with this Base Station. Otherwise, leave the Base Station System Name blank on the Satellite.

Location

Contact Name

Contact Email

Contact Phone

Object ID 1.3.6.1.4.1.11898.2.4.9

Ethernet MAC Address 00:20:A6:55:6E:EE

Descriptor Wireless Router v2.0.1(72) SN-05AT10590479 v3.0.4

Up Time (DD:HH:MM:SS) 00:00:46:17

Note: Change in Mode of Operation requires a device reboot and appropriate changes to IP Configuration.

Mode of Operation Bridge

Network

IP Configuration

Note:

Changes to these parameters require reboot in order to take effect.

IP Address Assignment Type StaticDynamic

IP Address

Subnet Mask

Default Router IP Address

Default TTL 64

Spanning Tree

Spanning Tree Status Disable

Bridge Priority

Max Age (1/100 sec.)

Hello Time (1/100 sec.)

Forward Delay (1/100 sec.)

Priority and Path Cost Table

Port	Priority	Path Cost	State	Status
1	0	100	Forwarding	Enable
2	0	100	Disabled	Enable

IP Routes

Local IP Addresses

IP Address	Subnet Mask	Interface
10.0.0.1	255.255.255.0	1
10.0.0.1	255.255.255.0	3

IP Routes

IP Address	Subnet Mask	Next Hop	Interface	Metric
0.0.0.0	0.0.0.0	10.0.0.1	1	0
10.0.0.0	255.255.255.0	10.0.0.1	1	0
127.0.0.1	255.255.255.255	127.0.0.1	0	0
169.254.152.248	255.255.255.255	10.0.0.1	1	0

System is not in routing mode. The above parameters are only configurable if the system is in routing mode. Make sure the system has been rebooted after changing from bridge to routing mode.